Package 'IDE'

July 21, 2025

Type Package

Title Integro-Difference Equation Spatio-Temporal Models

Version 0.3.1

Date 2022-05-30

Maintainer Andrew Zammit-Mangion <andrewzm@gmail.com>

Description The Integro-Difference Equation model is a linear, dynamical model used to model phenomena that evolve in space and in time; see, for example, Cressie and Wikle (2011, ISBN:978-0-471-69274-4) or Dewar et al. (2009) <doi:10.1109/TSP.2008.2005091>. At the heart of the model is the kernel, which dictates how the process evolves from one time point to the next. Both process and parameter reduction are used to facilitate computation, and spatially-varying kernels are allowed. Data used to estimate the parameters are assumed to be readings of the process corrupted by Gaussian measurement error. Parameters are fitted by maximum likelihood, and estimation is carried out using an evolution algorithm.

Imports methods, ggplot2, Matrix, sp, spacetime, parallel, dplyr, tidyr, FRK, DEoptim, stats, utils, sparseinv

Suggests knitr

BugReports https://github.com/andrewzm/IDE/issues/

Depends R (>= 3.6.0)

Encoding UTF-8

VignetteBuilder knitr

NeedsCompilation no

License GPL (>= 2)

RoxygenNote 7.2.0

Author Andrew Zammit-Mangion [aut, cre]

Repository CRAN

Date/Publication 2022-05-30 12:10:14 UTC

2 coef.IDE

Contents

Index																		8
	simIDE																	
	IDE show_kernel .																	
	constant_basis																	
	IDE-package coef.IDE																	. 2

IDE-package

Integro-difference equation

Description

The Integro-Difference Equation model is a linear, dynamical model used to model phenomena that evolve in space and in time. At the heart of the model is the kernel, which dictates how the process evolves from one time point to the next. Both process and parameter reduction are used to facilitate computation, and spatially-varying kernels are allowed. Data used to estimate the parameters are assumed to be readings of the process corrupted by Gaussian measurement error. Parameters are fitted by maximum likelihood, and estimation is carried out using an evolution algorithm.

coef.IDE

Retrieve estimated regression coefficients

Description

Takes a an object of class IDE and returns a numeric vector with the estimated regression coefficients.

Usage

```
## S3 method for class 'IDE'
coef(object, ...)
```

Arguments

```
object of class IDE ... currently unused
```

See Also

IDE for more information on how to construct and fit an IDE model.

Examples

```
SIM1 <- simIDE(T = 5, nobs = 100, k_spat_invariant = 1)
coef(SIM1$IDEmodel)</pre>
```

constant_basis 3

constant_basis

Create a single, constant basis function

Description

Constructs an object of class Basis as defined in FRK that is constant over the entire spatial domain.

Usage

```
constant_basis()
```

Value

Object of class Basis

See Also

IDE for how to use basis functions to construct the IDE kernel

Examples

```
basis1 <- constant_basis()</pre>
```

IDE

Construct IDE object, fit and predict

Description

The integro-difference equation (IDE) model is constructed using the function IDE, fitted using the function IDE. fit and used for prediction using the function predict.

Usage

```
IDE(
    f,
    data,
    dt,
    process_basis = NULL,
    kernel_basis = NULL,
    grid_size = 41,
    forecast = 0,
    hindcast = 0
)

fit.IDE(object, method = "DEoptim", fix = list(), ...)

## S3 method for class 'IDE'
predict(object, newdata = NULL, covariances = FALSE, ...)
```

4 IDE

Arguments

f R formula relating the dependent variable (or transformations thereof) to covari-

data object of class STIDF data

object of class difftime identifying the temporal discretisation used in the dt.

process_basis object of class Basis as defined in the package FRK

kernel_basis a list of four objects of class Basis as defined in the package FRK. The first

> corresponds to the spatial decomposition of the kernel amplitude, the second to the kernel aperture, the third to the kernel horizontal offset, and the fourth to the

kernel vertical offset. If left NULL, a spatially-invariant kernel is assumed

grid_size an integer identifying the number of grid points to use (in one dimension) for

numerical integrations

forecast an integer indicating the number of steps to forecast (where each step corre-

sponds to one difftime)

hindcast an integer indicating the number of steps to hindcast (where each step corre-

sponds to one difftime)

object object of class IDE to for fitting or predicting

method method used to estimate the parameters. Currently only "DEoptim" is allowed,

which calls an evolution algorithm from the package DEoptim

fix list of parameters which are fixed and not estimated (e.g., list(sigma2_eps =

0.01)). Currently only the measurement-error variance (sigma2_eps) can be

fixed

other parameters passed to DEoptim or predict

data frame or object of class STIDF containing the spatial and temporal points at newdata

which to predict

a flag indicating whether prediction covariances should be returned or not when covariances

predicting

Details

The first-order spatio-temporal IDE process model used in the package IDE is given by

$$Y_t(s) = \int_{D_s} m(s, x; \theta_p) Y_{t-1}(x) dx + \eta_t(s); \quad s, x \in D_s,$$

for $t=1,2,\ldots$, where $m(s,x;\theta_p)$ is a transition kernel, depending on parameters θ_p that specify "redistribution weights" for the process at the previous time over the spatial domain, D_s , and $\eta_t(s)$ is a time-varying (but statistically independent in time) continuous mean-zero Gaussian spatial process. It is assumed that the parameter vector θ_p does not vary with time. In general, $\int_{D_s} m(s, x; \theta_p) dx < 1$ for the process to be stable (non-explosive) in time.

The redistribution kernel $m(s,x;\theta_p)$ used by the package IDE is given by

$$m(s, x; \theta_p) = \theta_{p,1}(s) \exp\left(-\frac{1}{\theta_{p,2}(s)} \left[(x_1 - \theta_{p,3}(s) - s_1)^2 + (x_2 - \theta_{p,4}(s) - s_2)^2 \right] \right),$$

show_kernel 5

where the spatially-varying kernel amplitude is given by $\theta_{p,1}(s)$ and controls the temporal stationarity, the spatially-varying length-scale (variance) parameter $\theta_{p,2}(s)$ corresponds to a kernel scale (aperture) parameter (i.e., the kernel width increases as $\theta_{p,2}$ increases), and the mean (shift) parameters $\theta_{p,3}(s)$ and $\theta_{p,4}(s)$ correspond to a spatially-varying shift of the kernel relative to location s. Spatially-invariant kernels (i.e., where the elements of θ_p are not functions of space) are assumed by default. The spatial dependence, if present, is modelled using a basis-function decomposition.

IDE.fit() takes an object of class IDE and estimates all unknown parameters, namely the parameters θ_p and the measurement-error variance, using maximum likelihood. The only method currently used is the genetic algorithm in the package DEoptim. This has been seen to work well on several simulation and real-application studies on multi-core machines.

Once the parameters are fitted, the IDE object is passed onto the function predict() in order to carry out optimal predictions over some prediction spatio-temporal locations. If no locations are specified, the spatial grid used for discretising the integral at every time point in the data horizon are used. The function predict returns a data frame in long format. Change-of-support is currently not supported.

Value

Object of class IDE that contains get and set functions for retrieving and setting internal parameters, the function update_alpha which predicts the latent states, update_beta which estimates the regression coefficients based on the current predictions for alpha, and negloglik, which computes the negative log-likelihood.

See Also

show_kernel for plotting the kernel

Examples

show_kernel

Show IDE kernel

Description

Plotting function for visualising the IDE kernel.

6 simIDE

Usage

```
show_kernel(IDEmodel, scale = 1)
```

Arguments

IDEmodel object of class IDE

scale factor by which to scale the arrows when visualising a spatially-varying kernel

Details

The function show_kernel adapts its behaviour to the type of kernel. If the kernel is spatially-invariant, then the kernel with s evaluated at the origin is plotted. If spatially-variant, then arrows on a regular grid over the domain are plotted. The direction of the arrow is indicative of the transport direction at a specific location, while the length of the arrow is indicative of the transport intensity.

See Also

IDE for details on the IDE model.

Examples

```
SIM1 <- simIDE(T = 5, nobs = 100, k_spat_invariant = 0)
show_kernel(SIM1$IDEmodel)</pre>
```

simIDE

Simulate datasets from the IDE model

Description

Generates simulations that are then used to evaluate the fitting and prediction of an IDE model.

Usage

```
simIDE(T = 9, nobs = 100, k_spat_invariant = 1, IDEmodel = NULL)
```

Arguments

T number of time points to simulate

number of observations randomly scattered in the domain and fixed for all time

intervals

k_spat_invariant

flag indicating whether to simulate using a spatially-invariant kernel or a spatially-

variant one

IDEmodel object of class IDE to simulate form (optional)

simIDE 7

Details

The domain considered is [0,1] x [0,1], and an IDE is simulated on top of a fixed effect comprising of an intercept, a linear horizontal effect, and a linear vertical effect (all with coefficients 0.2). The measurement-error variance and the variance of the additive disturbance are both 0.0001. When a spatially-invariant kernel is used, the following parameters are fixed: $\theta_{p,1}=150,\,\theta_{p,2}=0.002,\,\theta_{p,3}=-0.1,\,$ and $\theta_{p,4}=0.1.$ See IDE for details on these parameters. When a spatially-varying kernel is used, $\theta_{p,1}=200,\,\theta_{p,2}=0.002,\,$ and $\theta_{p,3}(s),\,\theta_{p,4}(s)$ are smooth spatial functions simulated on the domain.

Value

A list containing the simulated process in s_df, the simulated data in z_df, the data as STIDF in z_STIDF, plots of the process and the observations in g_truth and g_obs, and the IDE model used to simulate the process and data in IDEmodel.

See Also

show_kernel for plotting the kernel and IDE

Examples

```
SIM1 <- simIDE(T = 5, nobs = 100, k_spat_invariant = 1)
SIM2 <- simIDE(T = 5, nobs = 100, k_spat_invariant = 0)</pre>
```

Index

```
coef.IDE, 2
constant_basis, 3
fit.IDE (IDE), 3

IDE, 2, 3, 3, 6, 7
IDE-package, 2
predict.IDE (IDE), 3
show_kernel, 5, 5, 7
simIDE, 6
```